

Phone

- [Emails on Phone](#)
- [Giacom 2016 Phone email setup - iOS](#)
- [Giacom 2016 Phone email setup - Android](#)
- [Yealink Phone Showing RPSing](#)

Emails on Phone

Android:

<https://support.google.com/work/android/answer/9412194?hl=en>

iPhone:

<https://support.microsoft.com/en-us/office/set-up-an-outlook-account-on-the-ios-mail-app-7e5b180f-bc8f-45cc-8da1-5cefc1e633d1>

Use your email address and usual log on password.

Tap Settings.

Tap Passwords & Accounts.

Tap Add Account.

Tap Exchange.

Tap Email and key in your email address - ..@..co.uk

Tap Password and key in the password for your email account. -

Tap Description and key in the required name - Company

Tap Next.

Tap Server and key in the server address -

Tap Domain and key in the domain name - *leave blank*

Tap Username and key in your username for the server - ...

Tap Password and key in the password for your email account -


Tap Next.

Tap the indicator next to the required data type to turn synchronisation for the specific data type on or off.

Tap Save.

Giacom 2016 Phone email setup - iOS

Tap Settings > Mail, Contacts, Calendars > Add Account > Exchange



Enter email address, password and description, then select **Next:**

●○○○○ O2-UK 3G 12:28 73%

[Cancel](#) Exchange [Next](#)

Email john.smith@smithindustrie...

Password ●●●●●●●●●●●●●●●●

Description john.smith@smithindustrie...

Exchange Device ID

Q W E R T Y U I O P

A S D F G H J K L

↑ Z X C V B N M ↵

.?123 space return

Your iOS device will now try to locate your Exchange Server. If necessary enter the appropriate Exchange server name from the table below, and tap **Next**

Server name : activesync.giacomcp.com

●○○○○ O2-UK 3G 12:28 73%

Cancel Account Done

Email john.smith@smithindustries.com

Server *activesync.giacomcp.com*

Domain Optional


Username john.smith@smithindustries.com

Password ●●●●●●●●

Description Exchange

Advanced Settings >

Upon completion you can choose which types of data to sync with your Exchange account:




PLEASE NOTE: To modify your Exchange settings, Tap **Settings** > **Mail** > **Contacts** > **Calendars**, select your Exchange account, and tap **Account Info**

Giacom 2016 Phone email setup - Android

From your Android home screen access your phone settings and then **Accounts**. Then select **Add Exchange ActiveSync** account.

Enter your Email address and Password. Check **Send email from this account by default** (available only if you have already added another email account) to set this as the default email account and then tap **Next**



< @ Add an Exchange ActiveSy..

Configure exchange account in a few steps

Email Account

.....

☐ Show password


☒ Send email from this account by default


Manual setup Next

Your device will attempt to automatically find the additional details needed to set up your account. If it is successful, you will skip to Step 5. If it cannot automatically find the additional details needed, you will see the message **Setup could not finish**. Tap **Edit details** or **configure manually** to enter the additional information manually

Enter the appropriate Exchange server name as in the screenshots below, select Use secure connection (SSL) and tap **Next**

Server name: activesync.giacomcp.com



<  Exchange server settings

Domain\user name

Email Address

Password

.....

Exchange server

activesync.giacomcp.com


☒ Use secure connection (SSL)

☐ Use client certificate


Client certificate

Next

Review the **Activation** screen. Uncheck the **Always show** option if you do not want to see this message again when setting up an ActiveSync account, and tap **OK**



The phone will then check the Exchange Server settings and display the Remote Security Administration message:



Tap **OK**

Yealink Phone Showing RPSing


If you have recently factory reset a Yealink handset then you may see the following notifications on your devices screen. '**input sn**' on the first line (*top left of the screen*) or '**RPSing**' on the account information on the web interface.

Yealink RPSing

In this blog, we will take you through a few short steps you can take to solve this issue and have your phones back up and running as soon as possible.


Step 1:

Click on the function key where '**input sn**' is located. You should then be presented with the following page:



Enter the last 5 digits of the serial number from the underside / back of the phone (Not the MAC address)

You get x5 attempts at entering the correct SN, if you enter the incorrect serial number you will get the following message:



Step 2:

Once you have entered the last 5 digits of the serial number the phone should then reset and boot up as normal.

Entering the serial number bounds the phone onto the Yealink RPS account.

If you run into any issues or would like more Yealink technical advice, please contact support@safetynet-it.com or call 0333 305 8224.